

V9 后台启动手册

1. 进入 domains/mydomain/bin 目录
2. 输入命令 `ps -ef |grep apusic`

```
domains/mydomain/bin# ps -ef |grep apusic
root      4234      3473  0 10:11 pts/0    00:00:00 /bin/sh ./startapusic
root      pid:4254      4234 99 10:11 pts/0    00:00:09 /usr/local/java/jdk1.8.0_202/bin/java -Djava.endorsed.dirs=/opt/Apusic/Apusicv9/lib/endorsed -Dcom.apusic.domain.home=/opt/Apusic/Apusicv9/domains/mydomain -server -Djava.net.preferIPv4Stack=true -Djava.security.egd=file:/dev/./urandom -Xms512m -Xmx1024m -XX:MaxPermSize=256m -classpath ./opt/Apusic/Apusicv9/classes:/opt/Apusic/Apusicv9/sp/*:jar:/opt/Apusic/Apusicv9/common/java.activation.jar:/opt/Apusic/Apusicv9/common/java.corba.jar:/opt/Apusic/Apusicv9/common/javase.jar:/opt/Apusic/Apusicv9/lib/apusic-client.jar:/opt/Apusic/Apusicv9/lib/apusic-embed.jar:/opt/Apusic/Apusicv9/lib/apusic-fastcgi-2.3.jar:/opt/Apusic/Apusicv9/lib/apusic-jms.jar:/opt/Apusic/Apusicv9/lib/apusic-sm-2.1.jar:/opt/Apusic/Apusicv9/lib/apusic-ws.jar:/opt/Apusic/Apusicv9/lib/apusic.jar:/opt/Apusic/Apusicv9/lib/d
```

3. 输入命令 `kill -9 pid(上图标注)`
4. 输入命令 `ps -ef |grep apusic` 查看是否已关闭

```
/domains/mydomain/bin# ps -ef |grep apusic
root      4445      3473  0 10:13 pts/0    00:00:00 grep --color=auto apusic
```

5. 输入命令 `nohup ./startapusic >/dev/null 2>&1 &` 启动 apusic

```
/domains/mydomain/bin# nohup ./startapusic >/dev/null 2>&1 &
[1] 4611
```

6. 打开浏览器输入网址 `localhost:6888/admin` 查看是否启动成功